

Blank Page Splitter

Revised 12-15-2008

Call 813-298-2474 <u>www.edocfile.com</u> Sales@edocfile.com

Blank Page Splitter

Purpose

Blank Page Splitter from eDocFile, is a utility that is designed for post processing of tiff images. It is ideally suited for use with a copier that scans tiff images to a file folder on the user's network. The program will watch this folder and when it finds a tiff image file it will silently open the file and move it to another file folder after it has split the document into separate files based upon the location of blank pages. It works with documents scanned in both simplex and duplex modes.

The simplex mode creates a new document every time a blank page is found. The duplex mode drops all blank pages and creates a new file when two consecutive blank pages are found. This allows a user to scan a mixture of simplex and duplex documents and have an output file with no blank pages.

The output file can be either a tiff image file or a PDF. A backup of the original image can also be saved in an archive folder.

System Requirements

Windows 2000 or Later A method of Acquiring Tiff Images – either a copier or a scanner Permission to Read and Write to an input and output folder as well as the program folder c:\splitit Adobe Acrobat or Reader to view output PDF's

Setup

Click on "Setup".

🗾 Main Menu				
i Bl	ANK PA	GE SPLITTER		
Program Operation				
Run Prog	ram	Setup 📕		
Help		Manual		
Exit				
Copyright© eDocFile Inc. 2004-2008				

The Setup Menu Will Open

🖳 Setup Blank Page Splitter 🛛 🛛 🔀						
SETUP BLANK PAGE SPLITTER						
For Blank Page File Separation:	For Blank Page Removal:					
If only the front side of the image is scanned use the simplex mode. If both sides are scanned use the duplex mode.	Scan a file to the Duplex Folder in either simplex or duplex mode					
Simplex Image Processing	Duplex Image Processing					
1 🗹 Process Simplex Images	4 🗹 Process Duplex Images					
c:\samplesimplexin 2	c:\sampleduplexin 5					
Browse to Folder where Multi-Page Simplex images are located	Browse to Folder where Multi-Page Duplex images are located					
c:\samplesimplexout 3	c:\sampleduplexout 6					
Browse to Output Folder For Simplex Images	Browse to Output Folder For Duplex Images					
General Settings						
7 🗹 Convert Processed image to PDF	11 🗹 Save origional Image in Archive Folder					
8 Monitor Function	c:\samplearchive 12					
9 10 Sensitivity Scale Enter between 1-10 *	Browse to Archive Folder					
10 10 Enter in Seconds how often to check for new images						
* The scale is based on the percent of black pixels where	Save Help Exit					
10 equals one percent Copyright© eDocFile Inc. 2004-2007						

To separate files that were scanned in a Simplex manner (only one side and each page needs to be saved) where the file needs to be split – Scan to the Simplex folder. Each time a blank page is found a new file will be created.

To separate files that contain mixed pages (in other words they were scanned in a duplex manner with some but maybe not all back sides need to be saved) scan to the duplex folder. Two consecutive blank pages must be found for a new file to be created and all blank pages will be dropped.

- 1. Place a check mark in "Process Simplex Images" to process the folder containing simplex images. If the incoming documents were scanned in a simplex mode, each time a blank page is found it will create a new document.
- 2. Browse to or enter the folder that will contain the incoming simplex tiff images from the copier.
- 3. Browse to or enter the folder that will contain processed simplex tiff images or PDFs.
- 4. Place a check mark here if the incoming documents were scanned in a duplex mode, each time two blank pages are found together a new file will be created. If only one blank page is found it will be eliminated,
- 5. Browse to or enter the folder that will contain the incoming duplex tiff images from the copier.
- 6. Browse to or enter the folder that will contain processed duplex tiff images or PDFs. (this can be the same folder as the output folder for processed simplex images.

- 7. Place a check mark in "Convert Processed Image to PDF" if the output desired is a PDF instead of a tiff image.
- 8. Place a check mark in "Monitor Function" to let the program run in the background and process images as they arrive. If left unchecked it will run once and then exit.
- 9. Enter a number for sensitivity. Usually this will be between 2 and 3. The scale relates to the percentage of black pixels on the page. Where 1 is 1/10 of one percent. Only testing on your own documents will allow this to be set correctly. An example for testing would be to type a 2 or three letter word on a page. And see when it is included or dropped.
- 10. Enter a time in seconds to check the folder for new images.
- 11. Place a check mark here to save a copy of the original file
- 12. Enter a path to store the original file if it is to be saved.

Click on Continue

Confirm	n
?	Start Blank Page Splitter and Remover Now?
	Yes No

Click on Yes to Start the Program or No to return to the Main Menu

Running the Program

To run the program click on "Run Program".



A flashing Icon will appear in the Sys tray when the program is running.



To stop the program click on "Shut Down"

🗾 Mair	n Menu		X		
đ	BLANK PA	GE SPLITTER			
Main Menu					
	Shut Down	Setup			
	Help	Manual			
	Exit				
Copyright© eDocFile Inc. 2004-2008					

Support

For assistance with either the trial version or full version of Blank Page Splitter please contact us at:

eDocfile Inc. 2709 Willow Oaks Drive Valrico, FL 33594 Phone 813-413-5599 sales@edocfile.com